

# Wasp

## BARCODE TECHNOLOGIES

[Portal](#) > [Knowledgebase](#) > [Software](#) > [Labeler](#) > [Version 7](#) > [Labeler - How To - Is there a way to control the spacing between a bar code and its related caption?](#)

---

### Labeler - How To - Is there a way to control the spacing between a bar code and its related caption?

Internal User - 2017-04-10 - in Version 7

Turn off the caption altogether in the Object Properties (right-click) for the barcode object, then use the Insert Text tool bar button to create a text box beneath the barcode object, formatting and positioning the text as you desire.