MASIS BARCODE TECHNOLOGIES

Portal > Knowledgebase > FAQs > Microsoft .NET Framework Repair and Uninstall/Reinstall Procedures

Microsoft .NET Framework Repair and Uninstall/Reinstall Procedures

Scott Leonard - 2022-12-14 - in FAQs

Background

Wasp software products rely on the Microsoft .NET Framework for many operations. Corruption in .NET can cause Wasp products to fail or give errors with no apparent Wasp-related cause. For example, a problem persists even after deleting and reinstalling all components of a Wasp software product.

Repairing the .NET Framework (and/or uninstalling & reinstalling) can resolve certain issues.

Procedures

A. Start with the Microsoft .NET Framework Repair Tool, then test whether the problem still occurs:

Microsoft .NET Framework Repair Tool

https://support.microsoft.com/en-us/help/2698555/microsoft-.net-framework-repair-tool-is-a vailable

B. If that doesn't fix the problem, the .NET Framework Cleanup Tool does a more thorough removal process. Then the desired components can be reinstalled.

Microsoft .NET Framework Cleanup Tool User's Guide (instructions & downloads): https://blogs.msdn.microsoft.com/astebner/2008/08/28/net-framework-cleanup-tool-users-guide/

Download the cleanup tool hosted by Wasp:

https://dl.waspbarcode.com/kb/tools/dotnetfx_cleanup_tool-to-4.7.2.zip

C. This procedure takes longer and has several PC reboots.

Uninstall:

- 1. Control Panel, Programs and Features. If any .NET shows in this list, note what version it is (for later reinstallation), then uninstall. Later versions of Windows don't list .NET in this list.
- 2. Still in Programs and Features, click Windows Features at the left. When the dialog box populates, expand any .NET components listed (could be multiple versions), uncheck all boxes within, then click OK. Don't reboot if prompted.
- 3. .NET Cleanup tool: Cleanup Now, then Exit when finished.
- 4. Reboot.
- 5. .NET Cleanup tool (again): Cleanup Now, then Exit when finished.
- 6. Reboot.

Reinstall:

7. Control Panel, Programs and Features, Windows Features, expand any .NET components

listed (could be multiple versions), check all boxes within then click OK.

8. Use downloaded installer (if necessary) to reinstall up to the desired version. Reboot if prompted.

Microsoft's .NET Downloads & Info (the Cleanup Tool link has all versions):

.NET Framework 4.6.1 (Offline Installer)

https://www.microsoft.com/en-us/download/details.aspx?id=49982

or

.NET Framework 4.5.2 (Offline Installer)

http://www.microsoft.com/en-us/download/details.aspx?id=42642

What's New in the .NET Framework

https://msdn.microsoft.com/en-us/library/ms171868%28v=vs.110%29

Additional Information

When .NET version numbers show up in error messages, log files, and Windows Event Viewer, this is evidence of .NET problems. These version numbers can be seen as subfolder names under C:\Windows\Microsoft.NET\, including v1.0.3705, v1.1.4322, v2.0.50727, v3.0, v3.5, v4.0.30319.

Error keywords & files that point to .NET problems:

mscorlib

mscorlib.dll

KERNELBASE.dll

An example from a Windows Application Event Log follows. Note that the version number matches .NET, not the installed Wasp component (which is v7.3).

Application: WaspInventoryWindowsService.exe

Framework Version: v4.0.30319

Description: The process was terminated due to an unhandled

exception.

Exception Info: System.FormatException

Later versions of Windows include some .NET components:

Windows 10 v1703 (Creators): 3.5.1, 4.7

Windows 10 v1607 (Anniversary): 3.5.1, 4.6.1

Windows 10 original: 3.5.1, 4.6

Windows 8: 3.5.1, 4.5.1

Windows 7: 3.5.1

.NET versions 4.5.2 & 4.6.1 are considered stable and good for Wasp software.

.NET versions 4.5.1 & 4.6 are known to cause problems with Wasp software.

Related Pages

- Labeler v7 crashes at launch; log file mentions "Insufficient memory" and "System.Windows.Media.Composition.DUCE.Channel.SyncFlush()"
- Windows Printer & Printing Subsystem problems
- WPL Print Driver Removal via Registry. Driver Wizard says it completed, but the "completed successfully" list is empty and no printer is actually installed.