



# WASP PROTECT

Portal > Knowledgebase > Software > CountIt - Error: "Settings to access printer 'name' are not valid." after deleting printer from Windows

---

## CountIt - Error: "Settings to access printer 'name' are not valid." after deleting printer from Windows

Scott Barnett - 2017-04-10 - in Software

Go to Start, Run, type regedit and click OK. Navigate to HKEY\_CURRENT\_USER\Software\Wasp Technologies\WaspCount\Grid Print Settings. There will be a key named PrinterName, with the data being the name of the deleted printer.

Right click on PrinterName and select Delete. When you next try to print from the View/Adjust screen, it will give you the Page Setup screen and allow you to select the correct printer.