



[Knowledgebase](#) > [Software](#) > [Labeler](#) > [Labeler - Installation - Labeler installed as Admin says it is in Demo mode when run as the user.](#)

Labeler - Installation - Labeler installed as Admin says it is in Demo mode when run as the user.

Internal User - 2017-04-10 - [Labeler](#)

The user needs to be given read/write access for the directory C:\Program Files\Wasp Technologies, and full control to the registry key HKEY_LOCAL_MACHINE\SOFTWARE\Wasp Technologies. After that, it should allow the user to open the program correctly.