

Wasp

BARCODE TECHNOLOGIES

Portal > Knowledgebase > Software > Labeler > Version 7 > Labeler v6: "Error=48
Description 'File Not found: WaspAct.dll' [Details : CheckForcedActivationNew]"

Labeler v6: "Error=48 Description 'File Not found:
WaspAct.dll' [Details : CheckForcedActivationNew]"

Internal User - 2022-12-09 - in Version 7

Details:

In Visual Basic 6, Error 48 means that waspact.dll failed to load.

Reason:

The Visual C++ 2005 Redistributable package (x86) was not installed properly. If for some reason this component fails to install properly, the error above happens.

Fix:

Download and install the Visual C++ 2005 (x86) Redistributable package from the Microsoft website:

<http://www.microsoft.com/en-us/download/details.aspx?id=3387>

Download and Run the "vcredist_x86.exe" installer.

After the installer finishes, Labeler should run properly.

If needed, this is the same file hosted by Wasp Barcode Technologies:

https://dl.waspbarcode.com/kb/tools/vcredist-2005_x86.exe